# Create a ServiceNow dynamic share



**Dynamic shares** allow for real time sharing of ServiceNow records as they are created, updated, and/or deleted. Creating a dynamic share for a table will allow you to sync records for that table with the records in another application instance. The **Dynamic Share** module under **Replicator** in ServiceNow lists your dynamic share records that specify the format, conditions, and destination of data that will be dynamic shared out of your ServiceNow instance.

#### blocked URL NOTE:

 Because this approach uses <u>business</u> rules to trigger sharing records out, if a user is updating records with <u>setWorkflow(false)</u> to turn off executing <u>business</u> rules (including async <u>business</u> rules), records will not be shared. In this case, consider using alternative approaches like <u>Scheduled Sync Up</u>, <u>Scheduled Bulk Shares</u> or Flow.

### **Prerequisites**

First, you will need to install DataSync for ServiceNow and run the Perspectium Finish Install scripts.

Set your initial Perspectium & Replicator properties.

1 Then, create a ServiceNow shared queue.

#### **Procedure**

To create a DataSync for ServiceNow dynamic share, follow these steps:



#### **Navigate to Dynamic Share**

In ServiceNow's left side navigation window, navigate to **Perspectium > Replicator > Dynamic Share** or simply type and then click on **Dynamic Share**.




#### **Click New**

At the top of the form next to Replicator Configurations, click the **New** button.



### **Choose Dynamic Share Type**

Select Business Rule and click the Submit button.



blocked URL NOTE: Once you select a type, you cannot change this dynamic share to the other type (i.e. change from **Business Rule** to **Flow** or vice versa). You will have to delete the dynamic share and create a new one.



#### Type a dynamic share name

In the Name field, type any name for your dynamic share.



### Choose a table to dynamic share

Click the dropdown next to **Table**. Then, search for and choose the table or database view whose data you want to dynamic share out of your ServiceNow instance.

blocked URL NOTE: sys\_audit and sys\_user\_has\_role tables cannot be selected since they do not support business rules.



### Make your dynamic share active

Check the Active box to activate your dynamic share and start sharing out record data dynamically.



### Choose an encryption method

Choose a method to encrypt the data that will be shared out from the Encryption Method dropdown. Cipher options include:

Encryption Method	Dynamic shared data will
TripleDES	be encrypted with Triple DES.
AES128	be encrypted with AES-128.
AES256	be encrypted with AES-256.  blocked URL NOTE: To ensure AES-256 encryption for your data, you will need to create an encryption and decryption key with at least 32 characters in the PSP Properties module.
Base64 Encode Only	have Base64 encoding only.
Unencrypted	not be encrypted.



### **Choose your trigger conditions**

Scroll down to the Trigger Conditions tab and check any or all of the following boxes:

Action	Record data will be shared out of your ServiceNow instance when
Create	new records are created.
Update	record data is changed.
Delete	records are deleted.




### Choose a target queue

Click the **Additional Settings** tab and then click the shared queue that you want to dynamic share your record data to.



#### **Click Submit**

Click the **Submit** button at the bottom of the form to save the configurations for your dynamic share.



• NOTE: The dynamic share will not save if an already existing dynamic have the same values in all the following fields: Table, C reate, Update, Delete, Target Queue and Conditions.

## Similar topics

- Create a ServiceNow dynamic share
- Interactive only
- Configure business rule timing and order
- Share base table records only
- Scheduled sync up

# **Contact Perspectium Support**



US: 1 888 620 8880

UK: 44 208 068 5953

support@perspectium.com