

Save Perspectium properties in the sys_properties table

Fluorine+

The **Save Perspectium properties in the sys_properties table** option in Perspectium Properties lets you improve overall performance of your Perspectium integration by saving all properties related to your Perspectium integration to ServiceNow's [System Property \(sys_properties\)](#) table. By default, this option is disabled, and your Perspectium-related properties are saved in the Perspectium Properties table ([u_psp_properties](#)). If you enable this option and then make changes to your Perspectium properties, you can then copy those properties to the Perspectium Properties table by disabling this option again.



Note: Enabling this option will write all of Perspectium's application properties to ServiceNow's **sys_properties** table. The application will then use this table to access all of its properties, increasing the frequency of access to this table and its caching. Please disable this option if you run into issues.

Prerequisites

⚠ First, you will need to [install Replicator for ServiceNow](#) and [run the Perspectium Finish Install scripts](#).

Procedure

To save your Perspectium properties in ServiceNow's System Property (sys_properties) table, follow these steps:

1

Access Perspectium Properties

Log into your sharing ServiceNow instance and navigate to **Perspectium > Control and Configuration > Properties**.

2

Save Perspectium properties in the sys_properties table

Check the box labeled **Save Perspectium properties in the sys_properties table**. Then, scroll to the bottom of the form and click **Save** to save your changes. It may take 2-3 minutes for this change to be applied to your ServiceNow instance as the system saves all Perspectium properties over to the sys_properties and rebuilds the system cache.

NOTE: If, after enabling this option, the **u_psp_properties** table is deleted, you can regenerate the **u_psp_properties** table by clicking **Perspectium > Control and Configuration > Finish Install > Confirm**.

NOTE: If enabling this option, be sure NOT to enter a value higher than 15000000 for the **com.perspectium.output_bytes_limit** property or a value higher than 8000 for the **com.perspectium.output_row_limit** property.

Similar topics

- [Share display values](#)
- [Set initial Perspectium & Replicator properties in ServiceNow](#)

Contact Perspectium Support



US: **1 888 620 8880**

UK: **44 208 068 5953**

support@perspectium.com