

# Perspectium Properties Overview

Listed are a few of the Perspectium properties needed for the application:

Property name	Description	Type	Default value
com.perspectium.outbound.default_disabled	Used to send messages to Perspectium Integration Mesh to monitor status of the Perspectium for ServiceNow application. <b>i NOTE:</b> If the Perspectium application cannot connect to the Default Mesh, this values will toggle to true	true /false	false
com.perspectium.scheduled_job.node	Specify node to run Perspectium Scheduled Jobs (Warning: Changing from default may affect performance) <b>i NOTE:</b> <ul style="list-style-type: none"><li>The value "Default" allows your ServiceNow instance choose which node to run scheduled jobs on</li><li>This feature is only available on ServiceNow production instances as developer instances only have one node</li></ul>	dropdown	Default
com.perspectium.enable_receipts	Generate receipts from messages received to view details about the data you are sharing to/subscribing.	true /false	false
com.perspectium.outbound.delete_immediately (DataSync) com.perspectium.observer.outbound.delete_immediately (Observer)	Deletes messages as soon as they are posted to the Integration Mesh, rather than updating them to <b>sent</b> and letting a different process delete the message. <b>i NOTE:</b> This can be used under systems with high volume to limit the different processes going to the Outbound Message tables.	true /false	false
com.perspectium.replicator.track_shared_records	Enable shared record tracking for dynamic shares.	true /false	true
com.perspectium.replicator.emoji_support	Enable emoji support for bulk and dynamic shares without the use of custom schema.	true /false	false
com.perspectium.outbound.enable_max	Limits the maximum number of messages in the Outbound Messages table. The maximum number of messages is declared in the com.perspectium.outbound.max_messages property.  If enabled, when the maximum number of messages is reached , old messages (older than 15 minute) will be deleted.	true /false	false
com.perspectium.outbound.max_messages	Maximum number of outbound messages in the Outbound Messages table. Once this maximum has been reached, no new messages will be placed into the Outbound Messages table until the table has less messages than the max.  This property is dependent on property <b>com.perspectium.outbound.enable_max</b> being enabled.	integer	10000