


Perspectium & Replicator properties in ServiceNow

Fluorine

Perspectium Properties

The **Perspectium Properties** module (under **Perspectium > Control and Configuration**) in ServiceNow contains your username and password to connect to the Perspectium Mesh (MBS).

Perspectium Properties also contains various configuration options for your share (MultiOutput Processing) jobs, outbound messages, and debugging logs.




The screenshot shows the 'Perspectium Properties' configuration page in the ServiceNow interface. The left sidebar has a menu with 'control and configuration' selected, and 'Perspectium' expanded. The main panel contains the following fields:

- The user name that is used for connecting to the Perspectium message bus:** A text field with the value 'admin'.
- The user password that is used for connecting to the Perspectium message bus (show decrypted value):** A password field with masked characters.
- The message bus input queue name for receiving ServiceNow data pip.in.servicenow:** A text field.
- The target Perspectium server or message bus endpoint:** A text field with the value 'https://qa.perspectium.net/

Replicator Properties

The **Replicator Properties** module (under **Perspectium > Replicator**) in ServiceNow contains your default encryption and decryption keys that are used for shared and subscribed data.

Replicator Properties also contains various configuration options for your bulk shares and inbound messages.



The screenshot shows the 'Perspectium Replicator Properties' configuration page in the ServiceNow interface. The left sidebar has a menu with 'replicator' selected, and 'Perspectium' expanded. The main panel contains the following fields:

- Enable messages to arrive at this instance:** A checkbox that is checked.
- Enable to allow the Replicator inbound messages to go to a state of ready instead of being consumed immediately. Thus allowing multiple configurable scheduled jobs to pick up messages and run concurrently:** A checkbox that is unchecked.
- Enable replicator to add display value fields (prefixed with 'dv_') for reference and choice fields:** A checkbox that is unchecked.
- Share fields that belong only to the selected table. Note that this is unusual and will result in missing fields from the base (parent) table:** A checkbox that is unchecked.
- Encryption key for encrypting replicator content shared (must be at least 24 characters long or at least 32 characters long for AES256) (show decrypted value):** A text field with masked characters.
- Decryption key used to decrypt replicator content subscribed (must be at least 24 characters long or at least 32 characters long for AES256) (show decrypted value):** A text field with masked characters.

Set your initial Perspectium & Replicator properties

Get started with Replicator for ServiceNow by setting up your initial properties.

Similar topics

- [Share display values](#)
- [Set initial Perspectium & Replicator properties in ServiceNow](#)

Contact Perspectium Support



US: 1 888 620 8880

UK: 44 208 068 5953

support@perspectium.com