

DataSync Agent configuration

Fluorine

The file that controls the configuration settings for Perspectium DataSync Agents is the **agent.xml** file. This file is automatically created within the Agent's **bin** directory upon installation. To make changes to the configuration settings for your DataSync Agent, open this **agent.xml** file in a text editing application and modify the directives described in the sections below.

NOTE: The directives described below are only the **essential** configurations that must be set for your DataSync Agent. For additional DataSync Agent configuration settings, see the **Similar topics** list below or browse the topics under [DataSync](#).

Share & subscribe

DataSync Agents can perform two main functions, **share** and **subscribe**. To enable these functions, nest one or many of the following directives within the **agent.xml**'s **<agent>** directive:

Directive	Description
<share>	An Agent configured with <share> functionality (also known as a producer) monitors static data sources and places messages from those sources into queues in the Perspectium Mesh.
<subscribe>	An Agent configured with <subscribe> functionality (also known as a consumer) monitors queues in the Perspectium Mesh and processes any messages in those queues, typically by routing those messages to a static data source.
	blocked URL NOTE: This is the more common use case for the DataSync Agent.

Message batching directives (optional)

To improve the performance for your DataSync Agent, you can optionally add some batching directives that specify what constitutes a batch of messages that will trigger message processing.

Directive	Description
<max_reads_per_connect>	Maximum number of messages to consumer per connection interval
<max_writes_per_connect>	Maximum number of messages to produce per connection interval
<polling_interval>	Batch size (in number of messages) to trigger the processing of messages in a queue
<skip_message_set_processing/>	Self-closing tag that disables Message Set posting for data shared from ServiceNow

Task & handler

The **<task>** directive defines a specific **<share>** or **<subscribe>** function that your DataSync Agent should perform. Multiple **<task>** directives can be nested within the **<share>** and **<subscribe>** directives, and individual configurations can be defined for each **<task>** by nesting further configuration directives (described in the following sections) within each **<task>**.

Directive	Description
<task>	Task that handles either sharing or subscribing. You can configure separate settings by defining directives within each <task> directive. You can also specify an instances attribute here and give it a value of 4 (default) so that 4 instances of your <share> or <subscribe> task can run concurrently, thus improving throughput for data processing. blocked URL NOTE: You do not need to enter a value within the <task> directive. Nest all configuration directives noted below within each of your <task> directives.
<task_name>	Name for your <task> blocked URL NOTE: Only alphanumeric characters, numbers, and underscores are permitted as values for <task_name> .
<handler>	Name of the Java handler class. In most cases, the value for this directive will be com.perspectium.replicator.sql.SQLSubscriber .

Task Configurations

Under the **<task>** directive are configurations related to the task your DataSync Agent is performing such as saving data to a database. These different configurations are as follows:

Message, instance, and schema connection

The `<message_connection>` and `<instance_connection>` directives define how your DataSync Agent connects to the Perspectum Mesh and ServiceNow instance, respectively. For your DataSync Agent to connect to your Salesforce organization, you will need to include the `<message_connection>` and `<schema_connection>` directives.

Directive	Required attributes	Description						
<code><message_connection></code>	<p>user = Perspectum Mesh username</p> <p>password = Perspectum Mesh password</p> <p>blocked URL NOTE: You can optionally base64 encode this password, and include the base64 encoded string after <code>encryptd</code>: for this attribute's value.</p> <p>queue = Perspectum Mesh queue name</p> <p>The <code>use_basic_consume</code> attribute will depend on the type of messaging protocol you will be using.</p> <p>e.g., https://mymesh.perspectum.net</p> <table border="1"> <thead> <tr> <th>Protocol</th><th>Value</th></tr> </thead> <tbody> <tr> <td>HTTPS</td><td><code>use_basic_consume = false</code></td></tr> <tr> <td>AMQPS</td><td><code>use_basic_consume = true</code></td></tr> </tbody> </table>	Protocol	Value	HTTPS	<code>use_basic_consume = false</code>	AMQPS	<code>use_basic_consume = true</code>	Perspectum Mesh URL e.g., https://mymesh.perspectum.net
Protocol	Value							
HTTPS	<code>use_basic_consume = false</code>							
AMQPS	<code>use_basic_consume = true</code>							
<code><instance_connection></code>	<p>user = ServiceNow instance username</p> <p>password = ServiceNow instance password</p> <p>blocked URL NOTE: You can optionally encrypt this password by entering <code>encrypt:</code> followed by the password for this attribute's value. For example, "<code>encrypt:password1</code>". This will encrypt the password the first time the Agent is run and change the attribute's value to "<code>encrypted:<encrypted_password></code>" to indicate as such.</p>	ServiceNow instance URL e.g., https://myinstance.service-now.com						
<code><schema_connection></code>	<p>user = Salesforce org username</p> <p>password = Salesforce org password</p> <p>blocked URL NOTE: You can optionally encrypt this password by entering <code>encrypt:</code> followed by the password for this attribute's value. For example, "<code>encrypt:password1</code>". This will encrypt the password the first time the Agent is run and change the attribute's value to "<code>encrypted:<encrypted_password></code>" to indicate as such.</p> <p>client_id = Salesforce Consumer Key for the Perspectum Replicator app</p> <p>client_secret = Salesforce Consumer Secret for the Perspectum Replicator app</p>	Salesforce org URL e.g., https://login.salesforce.com/services/oauth2/token						

Encryption key & decryption key

The `<encryption_key>` directive is used with `<share>` tasks to encrypt data that is being shared from a static data source to an application. The `<decryption_key>` directive is used with `<subscribe>` tasks to decrypt data that was encrypted by a sharing application. The value for the `<encryption_key>` directive should match the subscribing application's decryption key, and the value for the `<decryption_key>` direction should match the sharing application's encryption key.

Directive	Description
<code><encryption_key></code>	Encryption key used to encrypt data being shared from a static data source to an application
<code><decryption_key></code>	Decryption key used to decrypt data being shared from an application

Database

There are several directives related to your static data source, or database, that the DataSync Agent connects to. For more information on how to configure your database information in the `agent.xml` configuration file, see [Perspectum SQL Replicator Agent Configuration Guide](#).

Directive	Description
-----------	-------------

<database_type>	Type of database you are syncing your data to. Supported databases and associated values for the <database_type>:																				
	<table border="1"> <thead> <tr> <th>Supported database</th><th>Value to enter for <database_type></th></tr> </thead> <tbody> <tr> <td>Oracle</td><td>oracle</td></tr> <tr> <td>MS SQL Server</td><td>sqlserver</td></tr> <tr> <td>MySQL</td><td>mysql</td></tr> <tr> <td>Snowflake</td><td>snowflake</td></tr> <tr> <td>SAP Hana</td><td>hana</td></tr> <tr> <td>Amazon Redshift</td><td>redshift</td></tr> <tr> <td>IBM DB2</td><td>db2</td></tr> <tr> <td>HP Vertica</td><td>vertica</td></tr> <tr> <td>PostgreSQL</td><td>postgres</td></tr> </tbody> </table>	Supported database	Value to enter for <database_type>	Oracle	oracle	MS SQL Server	sqlserver	MySQL	mysql	Snowflake	snowflake	SAP Hana	hana	Amazon Redshift	redshift	IBM DB2	db2	HP Vertica	vertica	PostgreSQL	postgres
Supported database	Value to enter for <database_type>																				
Oracle	oracle																				
MS SQL Server	sqlserver																				
MySQL	mysql																				
Snowflake	snowflake																				
SAP Hana	hana																				
Amazon Redshift	redshift																				
IBM DB2	db2																				
HP Vertica	vertica																				
PostgreSQL	postgres																				
<database_server>	URL for your database. If your database is installed on your local machine, set this value to localhost .																				
<database_port>	Port number for your database																				
<database_user>	Username used to connect to your database																				
<database_password>	Password used to connect to your database																				
<database_parms>	(Optional) Can be used to pass additional parameters to the database server during establishment of the connection e.g., characterEncoding=UTF-8 & useSSL=false																				
<database>	Name of your database																				
<database_column_max_size>	Maximum size of an object that can appear in your database's columns																				
<database_sid>	SID used for your Oracle database NOTE: This directive is required for DataSync integrations to an Oracle database only.																				
<sql_retries>	(Optional) Can be used to configure the number of times the DataSync agent will retry after a SQLException. NOTE: This directive defaults to 3.																				
<sql_retries_delay>	(Optional) Can be used to configure how many milliseconds the DataSync agent will wait between retries. NOTE: This directive defaults to 250.																				

Data Guarantee

These directives configure how the DataSync agent works with [Data Guarantee](#).

Directive	Description
<receipt_send_interval>	(Optional) Indicates the number of seconds in which the Agent will regularly send receipts back to the sharing/publishing instance. NOTE: This directive defaults to 1800.

Example basic agent.xml configuration

The example below shows some of the basic configurations that must be set for a Perspectium DataSync Agent. For additional DataSync Agent configuration settings, see the [Similar topics](#) list below or browse the topics under [DataSync](#).

```

<?xml version="1.0" encoding="ISO-8859-1" standalone="no"?>
<config>
  <agent>
    <max_reads_per_connect>4000</max_reads_per_connect>
    <polling_interval>5</polling_interval>
    <skip_message_set_processing/>
    <share/>
    <subscribe>
      <task instances="4">
        <task_name>datasyncforservicenow_to_mysql_subscribe</task_name>
        <message_connection password="encrypted:v10tU71yu8N/EFIJH85SSBtaIt7qEEFvqiqft9VZyYE=" queue="psp.out.replicator.testqueue" user="admin" use_basic_consume="false">https://testperspectium.net</message_connection>
        <instance_connection password="encrypted:v10tU71yu8N/EFIJH85SSPN9aF0P5/YViVwPEVFcGW4=" user="test.user">https://myinstance.service-now.com</instance_connection>
        <handler>com.perspectium.replicator.sql.SQLSubscriber</handler>
        <decryption_key>The cow jumped over the moon</decryption_key>
        <database_type>mysql</database_type>
        <database_server>localhost</database_server>
        <database_port>3306</database_port>
        <database_user>root</database_user>
        <database_password>encrypted:v10tU71yu8N/EFIJH85SSMoilKLTeJHQrNZPJ7c5tFU=</database_password>
        <database_parms>characterEncoding=UTF-8 & useSSL=false</database_parms>
        <database_column_max_size>251</database_column_max_size>
        <database>psp_repl</database>
          <sql_retries>5</sql_retries>
          <sql_retries_delay>1500</sql_retries_delay>
      </task>
    </subscribe>
  </agent>
</config>

```

Similar topics

- Set up DataSync Agent to share to PostgreSQL
- Set up DataSync Agent to share to HP Vertica
- Set up temporal data
- Set up DataSync Agent to share to MySQL
- Skip altering of database tables

Contact Perspectium Support



US: 1 888 620 8880

UK: 44 208 068 5953

support@perspectium.com